**1.** Télécharger <u>VoiceMeeter</u>, l'installer puis redémarrer l'ordinateur.

2. Se rendre dans Tous les paramètres > Périphériques > Paramètres audio > Panneau de configuration Son.
Dans l'onglet Lecture, choisir VoiceMeeter Input comme périphérique par défaut.

aut-parleurs/écouteurs ealtek(R) Audio rêt	
<b>asque</b> E BOOM 2 hug Stereo éconnecté	
piceMeeter Input 8-Audio VoiceMeeter VAIO ériphérique par défaut	

Dans l'onglet **Enregistrement**, choisir **VoiceMeeter Output** comme périphérique par défaut.

Pise microphone   Relatekt(R) Audio   Non connecté   Relatekt(R) Audio   Piet   Sterce Mk   Reaftekt(R) Audio   Piet   WickMeeter Output   Vis-Audio VisionMeeter VAIO   Piet   Vis-Audio VisionMeeter VAIO			
Réseau de microphones Realtacit/Q Audio Prêt   Stereo Mix Realtacit/Q Audio Prêt   VoiceMeeter Output Vb-Audio VoiceMeeter VAID Yb-Audio VoiceMeeter VAID Yb-Audio VoiceMeeter VAID		Prise microphone Realtek(R) Audio Non connecté	
Stereo Mik Realitek(R) Audio Protection Control Vision Control	>	Réseau de microphones Realtek(R) Audio Prêt	
VoiceMeeter Output VB-Audio VoiceMeeter VAIO Périphérique par défaut		<b>Stereo Mix</b> Realtek(R) Audio Prêt	
		VoiceMeeter Output VB-Audio VoiceMeeter VAIO Périphérique par défaut	

## **3.** Lancer l'appli **VoiceMeeter**.

Effectuer les paramétrages suivants.

	Werene, while some where, or we were, or the solution of	term [] <sup>HH</sup> [] VE-AUDIO Softwar Julie Makanis in Sound Brok	VBAN	Menu _ X
HARDWARE INPUT Réseau de microphones (Realtek(R)	HARDWARE INPUT Stereo Mix (Reallek(R) Audio)	VIRTUAL INPUT VB-Audio Voicemeeter VAIO	A1 A2 HARDV Haut-par	Restart Audio Engine Auto Restart Audio Engine (A
INTELLIPAN AUDIBILITY VOICE Color Panel fr echo brokhress	INTELLIPAN AUDIBILITY	EQUALZER Bass Med High	- dB	Load Settings Load Settings on Startup: no file loaded !!! Save Settings
La 1 0.0	u 0.0			Reset Settings (Re-Initialization System Tray Run on Windows Startup Show App On Startup
0.0	0.0		3.9	Set as Always Visible Lock Graphic User Interface
				Run MacroButtons on Voicer Run other Voicemeeter tools.
B T	B T	B	Stereo	Shortcut Key (Hook) Limit Remote Gain to 0 dBfs
in the second se		iii () ∭	Comp osite	System Settings / Options M.I.D.I. Mapping VBAN Options (VB-Audio N VBAN Chat Room (VB-Aud
	Eader G		Fader Cal	Shut Down Voicemeeter About Online Help / Support







VoiceMeeter est maintenant correctement paramétré.

4. Dans Via, vérifier que le périphérique du microphone est VoiceMeeter Output.



Dans Ma Classe Virtuelle du CNED, vérifier que le microphone à partager est VoiceMeeter Output.



5. En cas de problème de son (lecture ou enregistrement), vérifier dans les propriétés des périphériques – Hautparleurs/écouteurs, VoiceMeeter Input, Réseau de microphones et VoiceMeeter Output – qu'ils sont activés et que les niveaux ne sont pas à zéro.

Propriétés de : Réseau de microphones	×
Général Écouter Niveaux Statistiques avancées	
Réseau de microphones	
Ampli microphone +20.0 dB	
OK Annuler	Appliquer
🚺 correct 🛛 🚺	ncorrect